

RELEASE EPROM RP100	CHECKSUM	DATE
V 1.00	4421	19/10/98
MODIFY		REFERENCE
1. First release		Laboratory
RELEASE EPROM RP100	CHECKSUM	DATE
V 1.01	E6AA	04/12/98
MODIFY		REFERENCE
1. Eliminated random click on performances GRAND PIANO, STRING PIANO, RHODEX 1, JAZZ ORGAN, THEATRE ORGAN e VIBES COMBO 2		Laboratory
2. Fixed bug on sequencer when change mode (Normal, Layer, Split) is recorded.		Laboratory
3. Improved precision of beat per minute		Laboratory
RELEASE EPROM RP100	CHECKSUM	DATE
V 1.02	CFD6	25/01/99
MODIFY		REFERENCE
1. Random total lockups happen when there is an over charge of notes and frequently damper events. The cause was an indefinitely interrupt pending. A check of all interrupt enable and disable has been made.		Baldwin
2. Ride cymbal is random truncated		Baldwin
3. Metronome best 'On/Off' functioning		Baldwin
4. 3 seconds increase of display hold time		Baldwin
RELEASE EPROM RP100 e RP150	CHECKSUM	DATE
V 1.03	F70F	23/02/99
MODIFY		REFERENCE
1. In record mode enter and exit from layer mode left undesired 8 sec. timing window.		Laboratory
2. Enabled handling of MIDI ext. START STOP CONTINUE commands.		Laboratory
3. Improved metronome enable and disable function.		Baldwin
4. Implemented a function that disable the 'D.P.M. and N.S.R.' by pressing for long time the grand piano key.		Baldwin
RELEASE EPROM RP90 e RP100 e RP150	CHECKSUM	DATE
V 2.00	7408 (ALL) DE44 (PR)	16/6/99
MODIFY		REFERENCE
1. Implemented the function that allow further firmware update through Computer serial interface.		Laboratory
2. Support the new model RP90		Laboratory
3. Fixed bug that caused a undesired metronome disable by exiting from demo mode.		Laboratory
4. Implemented periodic display refresh to recover a possible electrostatic disturb.		Laboratory
5. Improved Soft Pedal action by filtering increase.		Baldwin
RELEASE EPROM RP90 e RP100 e RP150	CHECKSUM	DATE
V 2.01	1817(ALL) 8253 (PR)	17/01/2000
MODIFY		REFERENCE
1. Now the micro tuning is displayed properly		Laboratory
2. Increased the decay time of Rhodex1 and Rhodex2		Baldwin
RELEASE EPROM RP90 e RP100 e RP150 e RP120	CHECKSUM	DATE
V 2.02	1978(ALL) 83B4 (PR)	17/05/2000
MODIFY		REFERENCE
1. Software for RP120 added		
RELEASE EPROM RP90 e RP100 e RP150 e RP120	CHECKSUM	DATE
V 2.03	F91B (ALL) 6357 (PR)	16/04/2002
MODIFY		REFERENCE
1. Corrected a bug that caused a whole failure on RP120 when the instrument is switched off during IMS function active.		SAT

<b>RP90 e RP100 e RP150 e RP120</b>		
<b>Model</b>	<b>ID</b>	<b>jumpers J4 , J5 , J3 , J6 , J2</b>
<b>RP100 GEM</b>	0	L , L , L , L , L
<b>RP100 BALDWIN</b>	1	L , L , L , L , H
<b>RP150 GEM</b>	2	L , L , L , H , L
<b>RP150 BALDWIN</b>	3	L , L , L , H , H
<b>RP90 GEM</b>	4	L , L , H , L , L
<b>RP90 BALDWIN</b>	5	L , L , H , L , H
<b>RP120 GEM</b>	6	L , L , H , H , L
<b>RP120 BALDWIN</b>	7	L , L , H , H , H